


Check Out Our Top Destinations Of The Month









Home Page

- 1. Users can go to Home Page by clicking on the logo in the header
- 2. Link to Flights Page
- 3. Link to Plan Page
- 4. If Users choose to log in, a pop-up window will appear like in (Fig. 1)
- 5.5. Country Location should automatically set itself to User's current location if their location services are on. If the User's location services are not on, icon will look like a globe and Users can click to open up a drop down and search for their country, like in (Fig.3)
- 6. 5. Country Location (above) also sets the 'From' in the Flights Search Box to the same country if the User's location services are not on, text inside the 'From' search bar will read 'Departure'.
- 7. Users can only choose one, and be able to switch between them. 'Return' will be selected automatically when page loads. Selected option will show with filled in circle like in (Fig.2)
- 8. Carousel of images with the names of the destinations which link to pages with itineraries and suggested flights relating to that location. Carousel changes locations every 5 seconds, animated transition should be a slide from right to left. Furthermore, Users can also manually scroll through by clicking the arrows on the sides, during which automatic slide animation should be disabled. Users can scroll both right to left and left to right. For clarification, sliding animation explained better with sketches in (Fig.4)
- 9. 'Discover More' button leads to page with information about flight insurance. Button animation in (Fig.5)
- 10. Page Shortcuts lead respective pages. 'Home' leads to Home Page, 'Flights' leads to Flights Page, etc.




Fig.1
Important to note, when this popup appears, the background becomes blurred




Fig.2





Fig.3







Fig.5



Home Page - Destination

- 1. On click, an overlay dropdown opens (*Fig.6*) *Destination Selection 1*. User can either select one of the top destinations from the suggestions in the overlay, or can start typing the location. If the User chooses to type, suggested destinations will change and filter according to what the user is typing. This field is compulsory, and if left empty by the time the user clicks the 'Search Flights' button, an error message will be displayed in small red text underneath "Please select destination country" and the box outline will turn red (*Fig.7*)
- 2. Once User clicks or types in the Destination, a list of airports available in that country appears to the right. If more than one airport is available in that Destination, at the top there will be '[Country] (All Airports)' listed as an option followed by the names of the individual airports listed in alphabetical order.
- 3. When User clicks their preferred choice, the overlay closes and the 'Destination' changes to their selection




Fig.6

From Malta	\longrightarrow To Lond	Ion Heathrow 3		
Depart Choose Date	Return Choose Date	Passengers, Class 1 Adult		
Return One-way	Search Flights			





Fig. 7
Above one can see the Flight
Search box with all errors that
can occur

Home Page - Dates






Fig.8

1. When User clicks on 'Departure Date' field, a calendar overlay opens up showing the current month of the current year. User can either click to select a day or type. If user chooses to type, the calendar will animate itself accordingly the same way as if the user chooses to click 2. Arrows at the top left and right of the calendar make it so User can switch the month currently displayed - left pointing arrow at top left switches to the previous month, and right pointing arrow at top right. switches to the next month. Previous month is only functional if the user has scrolled to a future month, and wishes to go back. The calendar does not allow the user to select or switch past months/dates 3. When a day is selected or typed in, the day is displayed on the calendar and it turns blue as shown in (Fig.8)







Fig.9

Home Page - Dates (cont.)

- 1. The calendar stays open once the Departure date is selected like in (Fig. 8) and user can choose the return date. The calendar switches fields once the return date is selected. If the User chooses to type, the same thing happens all animations will occur just the same but automatically as the User enters the day, month and year 2. The Return date is also highlighted in blue like the Departure date, and the days between the Departure date and Return date are highlighted in the same colour with a lower opacity
- 3. Once the User is happy with their selected dates, they can click 'Done' to close the calendar, upon which their selection is saved and displayed in the Depart and Return fields with the format of day/month/year as shown in (Fig.9)

Home Page - Passengers, Class





1. Upon click, an overlay opens up where User can edit the Passengers and flight Class (Fig.10). As the default, '1 Adult' and 'Economy' are selected



Fig.10


Home Page - Passengers, Class (cont.)





- 1. Users can increase and decrease the amount of Passengers using the + and symbols. The Adults default is 1, and therefore the is greyed out and cannot be clicked when the value is set to 1. This is the same for Children and Infants, but the default for these is 0
- 2. Users can click on 'Economy' to toggle a drop-down selection and choose the flight Class they want. By default, Economy Class is selected. Upon click, the drop-down closes and the chosen class is displayed. User can go back and re-open the menu and change their selection as many times as they want
- 3. Once the User is happy with their choices, they can click 'Done' and the overlay will close, saving their choices


Home Page - Search Flights



Above is shown the Search Flights box after the User has gone through each field and made the necessary selections

1. Once user has completed filling in all the fields, they can press the 'Search Flights' button to continue to the next page, loading the flights options. Button is animated as shown in (Fig.11). The User can still change any of the information in the fields before pressing the 'Search Flights' button





Flights Page - Flight Selection


- 1.From this page until payment, this bar will have highlighted in dark blue as shown, the step which corresponds to the page the User is on. If the. User goes back to the Home Page from here, the information inputted in previous steps in the Flights Search box will be lost, as everything will be reset. However, if the User chooses to go back from any of the steps in this bar up until the 'Flights' step, all information will be retained
- 2. Selected date is highlighted in dark blue as shown. Previous and next two days are shown on either side in muted greys, which can be selected and the flights shown will change to those available on that day. If User decides to select a day before their Selected date, in this case 5th June, then that date becomes the highlighted date in the middle, and the previous and next two days will change accordingly. In this way, the User can scroll through the calendar even at this stage. The calendar does not allow the User to scroll to a past date.
- 3. User can choose the 'Select' button to select that flight which will toggle the Fares Selection for that flight shown in the next page



Outbound Flight

Malta to London Heathrow





Inbound Flight

London Heathrow to Malta

8 June	9 June	10 June	11 June	12 June	
€185	€150	690	€200	C175	
17.00 _ London Heathrow	Duration 4hr 15min 21 1 Stops Ma	.15 Flight no. ita 2222		€90 Select Chick have to choose favo for all passangers	

Flights Page - Fares

- 1. This window is not an overlay, the page makes space for it to fit.
- 2. User can finalise their flight selection by choosing one of the Fares listed Basic, Value or Plus which can be done by clicking on the 'Select' button. This is animated like in (Fig.12). Once Button is clicked, the window showing the Fares closes and the flight options condense into one bar with the selected flight as shown in (Fig.13). This is the case for both the Outbound and Inbound flight selections






Fig.12





@ Copyright Traveling 2023

Continue 1

(f) (i) (ii)

Download Our App Now!

Google Play

Google Play

Download on the
App Store


Flights Page - Continue

1. Once User has chosen their Outbound and Inbound flights, the *'Continue'* button appears at the bottom which leads them to the Passengers page. The *'Continue'* button is animated as shown in *(Fig.14)*



Fig.14









Passengers Page

- 1. When User clicks this field, a drop-down appears as shown in (Fig.15). When User clicks on their preferred Title, the drop-down closes and their choice is saved. The User can change the title as many times as they want
- 2. If location services are on, or if User manually chooses the country location from the upper right corner on the Header, the country code is filled automatically. Otherwise, when User clicks this field, a drop-down with all country codes alongside a flag of that country will appear and user can click to select
- 3. The rest of the fields are type-in fields, where there is grey placeholder text to give a hint of what the User should type, but when they click in the field the text disappears and when they start typing the text is in black. All fields on this page must be filled correctly, and if User tries to continue to the next page without doing this, the fields will outline in red and an error message will appear underneath, as shown in (Fig. 16)
- 4. User must click this button to continue to the Seats page. This button is animated as shown in (Fig. 14)




Fig.15





Fig.16


Above one can see the Passengers input fields with all errors that can appear



Seats Page - Overview

- 1. Key showing different seat colours/appearances and what they mean
- 2. Seats selection box has two tabs that User can switch from one to the other by clicking the tab headings. The current tab is highlighted in dark blue. The default tab is the outbound flight, in this case 'Malta to London'
- 3. User can choose to continue without seat selection if a seat is not included in the price of the fare chosen


Seats Page - Outbound





- 1. User can click on the seats available to pick their seat. Once clicked, the seat turns bright blue to show it is selected
- 2. In conjunction to the seat on the diagram turning bright blue, this box displays the seat chosen in the format of [row number][LETTER IN CAPS]. The first selected seat goes to Passenger 1 and the second selected seat goes to Passenger 2 and so on. If there is a third passenger, the third selected seat will go to Passenger three, but if not it would go to Passenger 1.
- 3. User can either click on the 'Next flight' button or change tabs by clicking the Inbound flight tab in this case 'London to Malta'

Seats Page - Inbound


- 1. Once User chooses to move on the the inbound flight, this popup will show up. The 'Yes' button is animated as shown in (Fig.17) and the 'No' button is animated as shown in (Fig.18). If User selects 'Yes' then the same seats are selected for the return flight as shown in the bottom right image. If User selects 'No' then the User will repeat the process of manually selecting the seats as shown on the previous page.
- 2. Once all seats have been selected, User must click on this button to continue to the next page. This button is animated as shown in (Fig. 19)







Passenger 2 passengers	London to Malta Select for all passengers 3			Malta to London Select for all passengers		
Dr Heinz Doofenshmirz	-	0	+ 4	-	0	+
Ms Vanessa Doofenshmirz	-	0	+	-	0	+



Extras

- 1. Continue button is placed at the top of the page so that if the User does not want to add any Extras, they can quickly skip this page. This button is animated as shown in (*Fig.14*)
- 2. User must click on 'Select' to select which size check-in bag they want. When clicked this changes to 'Selected' as shown in (Fig.20). Users can click on this again to unselect. If a User wants to select both sizes, an additional table to select amounts will appear and be labelled as shown in (Fig. 23)
- 3. User can click on 'Select for all passengers' to add one of the selected check-in bag size to each passenger
- 4. User can add and remove check-in bags by pressing the + and symbols. Default value is set to 0. When 0 is displayed, the symbol is greyed out and cannot be clicked, however when the value is 1 or more the symbol is black and can be clicked to remove amount of bags. This is shown in (Fig.21)
- 5. Users can add insurance by clicking inside the boxes, which makes the box bright blue with a checkmark to show it is selected, as shown in (Fig. 22)




Fig.20




Fig.21







Fig.22





Review & Pay - Log In

- 1. Before payment, a Popup appears as the User is required to sign in if they already have an account or create one. By default, the pop-up window asks the User to Log in.
- 2. User can click in the input field to start typing. In the case of the Password field, characters are shown as dots as shown in (Fig.24) and user can click on the eye symbol to reveal the password.
- 3. User can click on 'Forgot password' which changes the contents of the window to show an input field for an email to reset their password as shown in (Fig.26)
- 4. User can select this box to remain signed in
- 5. User can choose to Sign Up using their Google account, Apple ID or Facebook credentials
- 6. Alternatively, Users can set up an account by clicking on 'Sign up here' which leads opens a new tab in the browser where Users can input all necessary details to create a new account
- 7. Once a User fills in their Log In details, they must click the 'Continue' button to proceed. If the credentials inputted are not correct, the fields are reset and an error message is displayed as shown in (Fig.25)








Fig.24 Fig.25

Forgot your password? Please enter your email address below and we will send you a link to reset your password **Email Address Reset Password** or log in

Review & Pay - Log In



- 1. This section shows a price break-down of what the User has selected
- 2. Once a User has logged in, the details will automatically be filled in based on previous purchases. Alternatively, the User can type in their details.
- 3. For the Expiry Date fields, the User can both type as well as click to show a drop down with the numbers they can select. Single digits will have a '0' in front
- 4. Once all the fields have been filled in, User must click the 'Pay Now' button to complete the purchase. This button is animated as shown in (Fig. 27). If any of the fields have incorrect or incomplete information, an error message will shown as shown in (Fig.28)



Fig.27




Fig.28

Above one can see the Payment input fields with all errors that can appear